


## Installing and Configuring the Liberty Player to Work with Your Foot Control

*\*Make sure your Foot Control is plugged into your computer*


1. Locate the Liberty software provided to you on a CD, insert the CD into your CD drive, browse to your CD drive, and open the folder labeled **Liberty Meeting Recorder\V1.0**. In this folder is a file named, **infinity.dll**.
2. Right-click on this file and select copy. You will need to paste this file in C:\Program Files\HighCriteria\LMRS.
3. Once the file has been copied, click **Start**, point to **Programs (All Programs** for Windows XP users), **Liberty Meeting Recording System** and then Click *Liberty Meeting Player*.




4. From the pull down menu, select View/Options/Foot Control. Put a check next to **Enable Foot Control**.



- Click the button labeled, [Foot Control Wizard](#). Complete the wizard.



- Once the wizard is complete, click [Set pedal functions](#). This dialog lets you assign functions for each device pedal and enables you to control the playback of sound data.



- Once you configured the foot pedals, click **OK**.
- Click **OK** to return to the Player window.